



Desoutter - ZAC de la Lorie - 38 rue Bobby Sands  
BP 10273 - 44818 Saint-Herblain Cedex - France

|          |            |
|----------|------------|
| Part no  | 6159275850 |
| Issue no | 21         |
| Language | English    |
| Date     | 18/07/2016 |
| Page     | 29         |

# Desoutter Protocol

CVIxxII – Release 4.2A and higher  
CVI3 – Release 1.6.9.x and higher

Release date: 18/07/2016

© Copyright 2016, Desoutter Saint Herblain France

All rights reserved. Any unauthorized use or copying of the contents or part thereof is prohibited. This applies in particular to trademarks, model denominations, part numbers and drawings. Use only authorized parts. Any damage or malfunction caused by the use of unauthorised parts is not covered by Warranty or Product Liability.

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 2/29       |                           |

## TABLE OF CONTENTS

|    |   |    |
|----|---|----|
| 1. | Change description .....                                    | 3  |
| 2. | Goal of the document .....                                  | 4  |
| 3. | CVIxII - Detailed tightening results .....                  | 4  |
|    | MID 7400: CVIxII – System event (Reserved) .....            | 4  |
|    | MID 7402: CVIxII - Cycle & phases results subscribe.....    | 4  |
|    | MID 7403: CVIxII - Cycle & phases results unsubscribe ..... | 5  |
|    | MID 7404: CVIxII - Phase result data .....                  | 5  |
|    | MID 7405: CVIxII - Phase result data acknowledge .....      | 8  |
|    | MID 7406: CVIxII - Cycle result data .....                  | 8  |
|    | MID 7407: CVIxII - Cycle result data acknowledge .....      | 9  |
| 4. | Curves (CVIxII & CVI3) .....                                | 10 |
|    | MID 7408: Last tightening curve data subscribe .....        | 10 |
|    | MID 7409: Last tightening curve data unsubscribe .....      | 11 |
|    | MID 7410: Last tightening curve data .....                  | 11 |
|    | MID 7411: Last tightening curve data acknowledge .....      | 12 |
| 5. | Cycle/Pset parameters modification.....                     | 13 |
|    | MID 7412: Cycle/Pset - Phase/Step parameters request.....   | 14 |
|    | MID 7413: Cycle/Pset - Phase/Step parameters data.....      | 14 |
|    | MID 7414: Change Cycle/Pset - Phase/Step parameters .....   | 17 |
| 6. | PSET selection & cordless tools .....                       | 22 |
|    | MID 7418: Select PSET within time frame (ExBCom tool) ..... | 22 |
|    | MID 7419: PSET selected within time frame .....             | 23 |
| 7. | Get information data from controller or tool.....           | 24 |
|    | MID 7420: Information data subscribe .....                  | 24 |
|    | MID 7421: Information data change event .....               | 25 |
|    | MID 7422: Information data change acknowledge.....          | 25 |
|    | MID 7423: Information data change unsubscribe.....          | 26 |
|    | MID 7424: Information data request.....                     | 26 |
|    | MID 7425: Information data reply .....                      | 27 |
| 8. | File transfer .....   | 28 |
|    | MID 7427: Transfer file (Pset settings).....                | 28 |
| 9. | Synthesis.....  | 29 |

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 3/29       |                           |

## 1. Change description

The following table describes the changes from one version of the specification to the next one:

| Status   | Release | Date       | Description  |
|----------|---------|------------|--|
| Official | 13      | 11/09/2012 | <b>1<sup>st</sup> official release of the documentation</b>                                  |
| Official | 14      | 12/12/2012 | Add Ncm and InOzf units in MID 7413  |
| Official | 15      | 04/04/2013 | MID 0041 rev 5 updated   |
| Official | 16      | 30/09/2013 | MID 7414 rev 1 fix doc issue : use parameters 10, not 11                                     |
| Draft    | 17-1    | 25/04/2014 | Add of MID 7418, 7419, 7420, 7421, 7422, 7423, 7424, 7425                                    |
| Draft    | 17-2    | 18/07/2014 | Official add of MID 7427, 7428, 7429   |
| Draft    | 17-3    | 23/10/2014 | Length corrected for MID 7418, 7419, 7427, 7428 and 7429                                     |
| Draft    | 17-4    | 15/12/2014 | Removed error case "Pset is already selected" for MID 7415.<br>Document format modifications |
| Draft    | 17-5    | 06/03/2015 | Precise Desoutter curves decoding  |
| Official | 17      | 22/04/2015 | Add CVI3 info for Cycle/Pset settings R/W commands.<br>Document format modifications         |
| Official | 18      | 14/10/2015 | ELRT & ERPHT tools can't have their cycle read or modified.                                  |
| Official | 19      | 27/01/2016 | Correction on curves decoding method.  |
| Official | 20      | 13/06/2016 | Update synthesis table   |
| Official | 21      | 27/01/2016 | Correction on curves decoding method.  |

## 2. Goal of the document

This document specifies the Desoutter protocol used to manage communication over ethernet between CVIxl or CVI3 tightening controllers and any external device, such as PLC, industrial PC, server, etc.

This protocol is an enhancement of the existing Open Protocol.

Specific commands (MIDs) are integrated in CVI controllers.

Both Open Protocol & Desoutter protocol are using the same communication port and mechanism.

Please refer to Open Protocol documentation for detailed information about communication structure, messages formats (headers, etc).

## 3. CVIxl - Detailed tightening results

### **MID 7400: CVIxl – System event (Reserved)**

Direction: CVIxl Controller → Integrator

Sent by the CVIxl controller every time a cycle has been modified.

No acknowledgement needed.

### **MID 7402: CVIxl - Cycle & phases results subscribe**

Direction: Integrator → CVIxl controller

| Header   |      |     |       | Data Field | Message End          |
|----------|------|-----|-------|------------|----------------------|
| 0020     | 7402 | Rev | Spare |            | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |       | 0 bytes    |                      |

This command is used to subscribe to the tightening results, from the controller.

The controller will then start to send phases results (MID 7404) and cycle results (MID 7406) event telegrams after every tightening.

Possible answers:

- Command accepted (MID 0005 with 7402 in data field).
- Command error (MID 0004 with error code 71: "Subscription already exists").

**Notes:** This subscription is related to both events: MID 7404 and MID 7406, which contains all the data related to phases & cycles tightening results.

It is not possible to only receive phase's results or cycle results.

## **MID 7403: CVIxl - Cycle & phases results unsubscribe**

Direction: *Integrator → CVIxl Controller*

| Header   |      |     |       | Data Field | Message End          |
|----------|------|-----|-------|------------|----------------------|
| 0020     | 7403 | Rev | Spare |            | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |       | 0 bytes    |                      |

This command is used to stop receiving phases and cycle results from the controller.

Possible answers:

- Command accepted (MID 0005 with 7403 in data field).
- Command error (MID 0004 with error 72: "Subscription does not exist").

## **MID 7404: CVIxl - Phase result data**

Direction: *CVIxl Controller → Integrator*

| Header   |      |     |       | Data Field               | Message End          |
|----------|------|-----|-------|--------------------------|----------------------|
| 0277     | 7404 | Rev | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |       | 257 bytes                |                      |

This event telegram contains the tightening results for the phase that has just been completed.

# Desoutter Protocol

The allocation of the variables in the data field is shown in the below table:

| Parameter      | Field Id | Nb Bytes | Description  |
|----------------|----------|----------|--|
| Spindle number | 01       | 2        | 01, etc.   |
| Cycle number   | 02       | 3        | 001, 002, etc.   |
| Phase number   | 03       | 2        | 01, 02, etc.   |
| Phase name     | 04       | 2        | Following names are defined for the phase names.<br>Please notice that the upper/lower case has to be considered<br>"S" = search sequence<br>"D" = rundown speed<br>"F" = final speed<br>"R" = run reverse<br>"V" = act on NOK<br>"J" = jump<br>"T" = prevailing torque<br>"W" = synchronization waiting<br>"d" = angle rundown<br>" " (space character) = empty phase |
| Method name    | 05       | 2        | This field indicates the tightening strategy used during the phase.<br>It is coded as following:<br>0 -> Torque only<br>1 -> Torque + Angle<br>2 -> Torque + Angle + Torque Rate<br>3 -> Angle + Torque<br>4 -> Angle + Torque + Torque rate<br>5 -> Torque + Current<br>6 -> Torque + Angle + Current   |
| M-             | 06       | 6        | xxxxxx value * 100 min. torque (lower limit)   |
| M+             | 07       | 6        | xxxxxx value * 100 max. torque (upper limit)   |
| M <sub>o</sub> | 08       | 6        | xxxxxx value * 100 torque safety limit   |
| M <sub>s</sub> | 09       | 6        | xxxxxx value * 100 angle threshold   |
| M <sub>A</sub> | 10       | 6        | xxxxxx value * 100 target torque   |
| M <sub>i</sub> | 11       | 6        | xxxxxx value * 100 measured torque   |
| W-             | 12       | 6        | xxxxxx value * 10 min. angle (lower limit)   |
| W+             | 13       | 6        | xxxxxx value * 10 max. angle (upper limit)   |
| W <sub>o</sub> | 14       | 6        | xxxxxx value * 10 safety angle   |
| W <sub>A</sub> | 15       | 6        | xxxxxx value * 10 target angle   |
| W <sub>i</sub> | 16       | 6        | xxxxxx value * 10 measured angle (phase)   |
| t-             | 17       | 6        | Reserved   |
| t+             | 18       | 6        | Reserved   |
| t <sub>A</sub> | 19       | 6        | Reserved   |
| t <sub>i</sub> | 20       | 6        | Reserved   |
| n              | 21       | 6        | xxxxxx Speed in %  |
| -              | 22       | 6        | Reserved   |
| -              | 23       | 6        | Reserved   |
| -              | 24       | 2        | Reserved   |
| -              | 25       | 6        | Reserved   |
| -              | 26       | 6        | Reserved   |
| CurveIndex1    | 27       | 4        | xxxx Index of the first point of the curve corresponding to this phase (1-500)<br>Value has the range 1001 to 1500 in case of buffer overrun   |
| CurveIndex2    | 28       | 4        | xxxx Index of the last point of the curve corresponding to this phase (1-500)<br>Value has the range 1001 to 1500 in case of buffer overrun  |
| -              | 29       | 6        | Reserved   |
| -              | 30       | 6        | Reserved   |
| -              | 31       | 6        | Reserved   |
| -              | 32       | 6        | Reserved   |
| -              | 33       | 6        | Reserved   |
| -              | 34       | 6        | Reserved   |
| Report         | 35       | 10       | status (see next table)  |

## Desoutter Protocol

### Phase "Report" field:

It's possible to get the phase status in the "Report" field of MID 7404.

This 10 ASCII characters of the "Report" field are the representation of a 32bits bit field:

| Position  | Name              | Length (bits) | Mask       | Description   |
|-----------|-------------------|---------------|------------|---|
| 28 ... 31 | Tightening type   | 4             | 0xF0000000 | 0 -> Torque only<br>1 -> Torque + Angle<br>2 -> Torque + Angle + Torque Rate<br>3 -> Angle + Torque<br>4 -> Angle + Torque + Torque rate<br>5 -> Torque + Current<br>6-> Torque + Angle + Current |
| 26 .. 27  | Unused            | 2             | 0x0C000000 | N / A   |
| 25        | Not Finished      | 1             | 0x02000000 | Spindle didn't finish the cycle   |
| 24        | Synchronisation   | 1             | 0x01000000 | SYN error   |
| 23        | External stop     | 1             | 0x00800000 | Cycle finishes due to external stop input   |
| 22        | Time out          | 1             | 0x00400000 | Information showing time (max) reached  |
| 21        | lmax              | 1             | 0x00200000 | Information showing lmax has been reached   |
| 20        | Trigger           | 1             | 0x00100000 | Trigger released before end of cycle  |
| 19        | Slave error       | 1             | 0x00080000 | N / A   |
| 18        | Group             | 1             | 0x00040000 | N / A   |
| 17        | Prog              | 1             | 0x00020000 | Program error (bad cycle parameters)  |
| 16        | SPI               | 1             | 0x00010000 | Connection with tool is faulty  |
| 15        | Flex              | 1             | 0x00008000 | Connection with FPGA is faulty  |
| 14        | Thermal contact   | 1             | 0x00004000 | Tool is overheaten  |
| 13        | Surgeguard        | 1             | 0x00002000 | Surge guard is faulty   |
| 12        | Overcurrent       | 1             | 0x00001000 | An overcurrent error has occurred   |
| 11        | Accelaration rate | 1             | 0x00000800 | Error during acceleration phase   |
| 10        | C1/C2             | 1             | 0x00000400 | N / A   |
| 09        | MMAX              | 1             | 0x00000200 | Monitoring over top limit   |
| 08        | Mmin              | 1             | 0x00000100 | Monitoring under low limit  |
| 07        | TMAX              | 1             | 0x00000080 | Time over top limit   |
| 06        | Tmin              | 1             | 0x00000040 | Time under low limit  |
| 05        | RMAX              | 1             | 0x00000020 | Torque Rate over top limit  |
| 04        | Rmin              | 1             | 0x00000010 | Torque Rate under low limit   |
| 03        | AMAX              | 1             | 0x00000008 | Angle over top limit  |
| 02        | Amin              | 1             | 0x00000004 | Angle under low limit   |
| 01        | TMAX              | 1             | 0x00000002 | Torque over top limit   |
| 00        | Tmin              | 1             | 0x00000001 | Torque under low limit  |

Example: if the start trigger is released before the end of cycle, bit 20 'trigger' will be set

## Notes:

- The curves are stored in a circular buffer. This means, if 500 points are stored for a curve, a new point will overwrite the oldest point of this curve. There is an over-run of the curve buffer, if the tightening duration is higher than the duration that has been set in the menu Parameters>Curves of the controller. The whole curve is sampled and displayed if the curve duration is higher than the tightening duration. A value between 1001 and 1500 for the CurveIndex1, indicates an over-run of the buffer, so the curves for the beginning of the tightening are not available. There is a maximum of 500 points stored.
- The results of the measurements are in the data field with the following Ids:
  - 11: tightening torque (M<sub>I</sub>)
  - 16: tightening angle (W<sub>I</sub>)
  - 20: tightening time (t<sub>I</sub>)
  - 35: result status

## MID 7405: CVIxlI - Phase result data acknowledge

Direction     *Integrator → CVIxlI Controller*

| Header   |      |     |       | Data Field | Message End          |
|----------|------|-----|-------|------------|----------------------|
| 0020     | 7405 | Rev | Spare |            | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |       | 0 bytes    |                      |

This telegram must be sent by the integrator to acknowledge the results of a phase (MID 7404) that has just been received.

## MID 7406: CVIxlI - Cycle result data

Direction:     *CVIxlI Controller → Integrator*

| Header   |      |     |       | Data Field               | Message End          |
|----------|------|-----|-------|--------------------------|----------------------|
| 0140     | 7406 | Rev | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |       | 120 bytes                |                      |

This event telegram contains the tightening results for the cycle that has just been completed.



|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 9/29       |                           |

The allocation of the variables in the data field is shown in the below table:

| Parameter             | Id | Bytes | Description   |
|-----------------------|----|-------|---|
| Spindle number        | 01 | 2     | 01, etc.  |
| Cycle number          | 02 | 3     | 001, 002, etc.  |
| VIN number            | 03 | 25    | The VIN number is 25 byte long and is specified by 25 ASCII characters taken between 0x20 and 0x7F Hex.   |
| Time stamp            | 04 | 19    | Time stamp for each tightening sent to the control station. The time stamp is 19 byte long and is specified by 19 ASCII characters (YYYY-MM-DD:HH:MM:SS). |
| Spindle name          | 05 | 11    | Name of the spindle (ex. ERAL1.5-70)  |
| Spindle serial number | 06 | 11    | Serial number of the spindle  |
| Tool total Count      | 07 | 10    | It's the total number of tightenings of the tool  |
| Tool partial count    | 08 | 10    | It's the partial number of tightenings of the tool  |
| Batch size            | 09 | 3     | Batch size of the considered cycle  |
| Batch count           | 10 | 3     | Batch count (number of OK tightenings)  |
|                       |    |       |   |

### **MID 7407: CVIxlI - Cycle result data acknowledge**

Direction: CVIxlI Controller → Integrator

| Header   |      |     |       | Data Field | Message End          |
|----------|------|-----|-------|------------|----------------------|
| 0020     | 7407 | Rev | Spare |            | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |       | 0 bytes    |                      |

This telegram must be sent by the integrator to acknowledge the result of a cycle (MID 7406) that has just been received.

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 10/29      |                           |

## 4. Curves (CVI12 & CVI3)

It is possible to get curves (graphs) information after every tightening using Desoutter protocol.

Each curves are filled with measurement points for the defined cycle time.

CVI12 controllers handle up to 500 points per curve.

CVI3 controllers handle up to 2000 points per curve. (FW min 1.6.6.x)

**Note:** For CVI12 controller, the limits between the different phases of a cycle are transferred in the phase result telegram ([MID7404](#)) using 2 markers, CurveIndex1 and CurveIndex2, indicating the number of first sample and the number of the last sample. It's then possible for the integrator to display markers for each phase when building the curve.

### ***MID 7408: Last tightening curve data subscribe***

Direction     *Integrator → Controller*

| Header   |      |     |             |            |            |       | Data Field | Message End       |
|----------|------|-----|-------------|------------|------------|-------|------------|-------------------|
| 0020     | 7408 | Rev | No Ack flag | Station ID | Spindle ID | Spare |            | NULL (ASCII 0x00) |
| 20 bytes |      |     |             |            |            |       | 0 bytes    |                   |

This command is used to subscribe to the last tightening curve from the controller.

The controller will then start to send curves information (MID 7408) event telegrams after every tightening.

Possible answers:

- Command accepted (MID 0005 with 7408 in data field).
- Command error (MID 0004 with error code 71: "Subscription already exists").

**Note:** Each tightening curve is split in several 7408 frames.

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 11/29      |                           |

## ***MID 7409: Last tightening curve data unsubscribe***

Direction: *Integrator → Controller*

| Header   |      |     |             |            |            |       | Data Field | Message End       |
|----------|------|-----|-------------|------------|------------|-------|------------|-------------------|
| 0020     | 7409 | Rev | No Ack flag | Station ID | Spindle ID | Spare |            | NULL (ASCII 0x00) |
| 20 bytes |      |     |             |            |            |       | 0 bytes    |                   |

This command is used to stop receiving last tightening curve from the controller.

Possible answers:

- Command accepted (MID 0005 with 7409 in data field).
- Command error (MID 0004 with error 72: "Subscription does not exist").

## ***MID 7410: Last tightening curve data***

Direction: *Controller → Integrator*

| Header       |      |     |             |            |            |       | Data Field            | Message End       |
|--------------|------|-----|-------------|------------|------------|-------|-----------------------|-------------------|
| 91 + N bytes | 7410 | Rev | No Ack flag | Station ID | Spindle ID | Spare | Data (See next table) | NULL (ASCII 0x00) |
| 20 bytes     |      |     |             |            |            |       | 71 + N bytes          |                   |

| Parameter             | Bytes | Description   |
|-----------------------|-------|---|
| Tool number           | 01-02 | 01  |
|                       | 03-04 | Tool number (01, 02, ... ,51, 52, ...)  |
| Pset number           | 05-06 | 02  |
|                       | 07-09 | Pset/Cycle number (001, 002, ... , 250).  |
| Time Coefficient      | 10-11 | 03  |
|                       | 12-25 | Time coefficient to be applied to each curve point  |
| Torque Coefficient    | 26-27 | 04  |
|                       | 28-41 | Torque coefficient to be applied to each torque value   |
| Angle Coefficient     | 42-43 | 05  |
|                       | 44-57 | Angle coefficient to be applied to each angle value   |
| Nb measurement Points | 58-59 | 06  |
|                       | 60-63 | Total number of points in the curve (xxxx)  |
| Nb Telegrams (frames) | 64-65 | 07  |
|                       | 66-67 | Total number of curve telegrams (MID7410) for this curve (xx)   |
| Id Telegram (frame)   | 68-69 | 08  |
|                       | 70-71 | Current curve telegram number (xx)  |
| Curve Data            | 72-.. | Curve Raw Data: (raw bytes values formatted in big endian).<br>A frame can contain up to 125 curve points of torque & angle.<br><i>see detailed explanation below</i> |

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 12/29      |                           |

### Curve raw data explanation:

Before being transferred, the curve raw data (torque & angle values) are encoded by the controller. This is due to the fact that Open protocol is an ASCII protocol and 'null values' (0x00) can't be transmitted or it will disrupt the communication ('null value' 0x00 is used to delimitate the "message end" of a frame).

The CVI controller encodes the curve raw data (torque & angle values) by adding +1 to each byte and modifying the possible 0x00 & 0xFF bytes values by 0xFFFE & 0xFFFF.

Each frame can contains up to 125 torque & angle values.

Torque values are defined in a 2 bytes ('ushort').

Angle values are defined in a 4 bytes ('ulong').

The size of curve raw data can be 750 bytes long ( $125 \times (2+4)$ ) + extra bytes because of the encoding of the 0x00 & 0xFF values (0xFFFE & 0xFFFF).

### Curve raw data decoding procedure:

- Analyze every byte to find any 0xFFFE and replace them by 0x00.
- Analyze every byte to find any 0xFFFF and replace them by 0xFF.
- Remove - 1 to each byte. For value = 0x00, applying -1 generates an overflow, so the result is 0xFF.
- Swap group of bytes for torque (2 bytes) & angle (4 bytes) values.

Torque : AB CD => CD AB

Angle: AB CD 12 34 => 34 12 CD AB

Swap example:

4A005D1A00004A005D1A00005B00...

Swap Torque & Angle bytes:

004A00001A5D004A00001A5D005B...

## MID 7411: Last tightening curve data acknowledge

Direction: Integrator → Controller

| Header   |      |     |             |            |            |       | Data Field | Message End       |
|----------|------|-----|-------------|------------|------------|-------|------------|-------------------|
| 0020     | 7411 | Rev | No Ack flag | Station ID | Spindle ID | Spare |            | NULL (ASCII 0x00) |
| 20 bytes |      |     |             |            |            |       | 0 bytes    |                   |

This telegram must be sent by the integrator to acknowledge the tightening curve data (MID 7410) that has just been received.

## 5. Cycle/Pset parameters modification

It is possible to modify parameters (torque, angle, speed, etc) of an existing cycle/Pset using Desoutter protocol.

**Note:** it is not possible to modify the cycle/Pset structure (add or remove phases/steps, change its type, etc).

The following table shows which parameters are accessible for each type of phase/step:

| Phase/Step<br>Parameters                    | Search sequence | Final speed / Tightening : A + T mon. | Final speed / Tightening : T + A mon. | Final speed / Tightening : Torque only | Final speed / Tightening : T + A + T. rate | Final speed / Tightening : A + T + T. rate | Final speed / Tightening : T + C mon. | Final speed / Tightening : T + A + C mon. | Run Reverse / Loosening : A + T mon. | Run Reverse / Loosening : T + A mon. | Run Reverse / Loosening : Torque only | Rundown speed | Action on NOK | Prevailing Torque - Forward | Prevailing Torque - Backward | Jump / Synchro | Seating Detection | Post Seating Detection |
|---|-----------------|---------------------------------------|---------------------------------------|--|--|--|---------------------------------------|---|--------------------------------------|--------------------------------------|---------------------------------------|---------------|---------------|-----------------------------|------------------------------|----------------|-------------------|------------------------|
| CVIxlI                                      | x               | x                                     | x                                     | x                                      | x  | x  | x                                     | x   | x                                    | x                                    | x                                     | x             | x             | x                           | x                            | x              | x                 | x                      |
| CVI3 (fw 1.6.9.x min)                       |                 | x                                     | x                                     |  | x  | x  |                                       | x   | x                                    | x                                    |                                       |               | x             | x                           | x                            | x              | x                 |                        |
| Phase type (read only)                      | x               | x                                     | x                                     | x                                      | x  | x  | x                                     | x   | x                                    | x                                    | x                                     | x             |               |                             |                              | x              | x                 | x                      |
| Tightening strategy type (read only)        |                 | x                                     | x                                     | x                                      | x  | x  | x                                     | x   | x                                    | x                                    | x                                     |               |               |                             |                              |                |                   |                        |
| Min torque                                  |                 | x                                     | x                                     | x                                      | x  | x  | x                                     | x   | x                                    | x                                    | x                                     |               |               | x                           | x                            |                | x                 | x                      |
| Max torque                                  |                 | x                                     | x                                     | x                                      | x  | x  | x                                     | x   | x                                    | x                                    | x                                     |               |               | x                           | x                            |                | x                 | x                      |
| Target torque                               |                 |                                       | x                                     | x                                      | x  |  | x                                     |   |                                      | x                                    | x                                     | x             |               |                             | x                            |                |                   |                        |
| Angle Threshold                             |                 | x                                     | x                                     |  | x  | x  |                                       | x   | x                                    | x                                    |                                       |               |               | x                           | x                            |                | x                 |                        |
| Min angle                                   |                 | x                                     | x                                     |  | x  | x  |                                       | x   | x                                    | x                                    |                                       | x             |               |                             |                              |                | x                 | x                      |
| Max angle                                   |                 | x                                     | x                                     |  | x  | x  |                                       | x   | x                                    | x                                    |                                       |               |               |                             |                              |                | x                 | x                      |
| Target angle or Back Angle 2 (prev.)        |                 | x                                     |                                       |  | x  |  |                                       | x   | x                                    |                                      |                                       |               |               | x                           | x                            |                |                   |                        |
| Safety/Abort torque                         |                 | x                                     |                                       |  | x  |  |                                       | x   | x                                    | x                                    | x                                     |               |               | x                           |                              |                | x                 | x                      |
| Safety/Abort angle                          |                 |                                       | x                                     |  | x  |  |                                       |   |                                      | x                                    |                                       |               |               |                             | x                            |                | x                 | x                      |
| Direction /Rotation                         | x               | x                                     | x                                     | x                                      | x  | x  | x                                     | x   | x                                    | x                                    | x                                     | x             | x             | x                           | x                            |                |                   |                        |
| Interphase time /Post step delay            | x               | x                                     | x                                     | x                                      | x  | x  | x                                     | x   | x                                    | x                                    | x                                     | x             |               | x                           | x                            |                |                   |                        |
| Speed                                       | x               | x                                     | x                                     | x                                      | x  | x  | x                                     | x   | x                                    | x                                    | x                                     | x             | x             | x                           | x                            |                |                   |                        |
| Rotation type                               | x               |                                       |                                       |  |  |  |                                       |   |                                      |                                      |                                       |               | x             | x                           | x                            |                |                   |                        |
| Stop : time / angle or Back Angle 1 (prev.) | x               |                                       |                                       |  |  |  |                                       |   |                                      |                                      |                                       |               | x             | x                           | x                            |                |                   |                        |
| Number of rotations                         | x               |                                       |                                       |  |  |  |                                       |   |                                      |                                      |                                       |               |               |                             |                              |                |                   |                        |
| End slope(Nm/°)                             |                 |                                       |                                       |  |  |  |                                       |   |                                      |                                      |                                       |               |               |                             |                              |                | x                 |                        |
| Delay (°)                                   |                 |                                       |                                       |  |  |  |                                       |   |                                      |                                      |                                       |               |               |                             |                              |                | x                 |                        |
| Number of samples                           |                 |                                       |                                       |  |  |  |                                       |   |                                      |                                      |                                       |               |               |                             |                              |                | x                 |                        |
| Gradient torque                             |                 |                                       |                                       |  |  |  |                                       |   |                                      |                                      |                                       |               |               |                             |                              |                |                   | x                      |
| Gradient angle                              |                 |                                       |                                       |  |  |  |                                       |   |                                      |                                      |                                       |               |               |                             |                              |                |                   | x                      |

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 14/29      |                           |

## MID 7412: Cycle/Pset - Phase/Step parameters request

Direction: Integrator → Controller

| Header   |      |     |             |            |            |       | Data Field               | Message End          |
|----------|------|-----|-------------|------------|------------|-------|--------------------------|----------------------|
| 0029     | 7412 | Rev | No Ack flag | Station ID | Spindle ID | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |             |            |            |       | 9 bytes                  |                      |

| Parameter         | Bytes | Description                               |
|-------------------|-------|---|
| Cycle/Pset number | 1-2   | 01  |
|                   | 3-5   | Cycle/Pset number 3 ASCII digits. Max 999 |
| Phase/Step number | 6-7   | 02  |
|                   | 8-9   | Phase/Step number 2 ASCII digits. Max 99  |

This command is used to read (get) a cycle/Pset - phase/step parameters in the controller.

**Note:** This command can't be used with ELRT pulse tools and ERPHT tools.

Possible answers:

- Parameters data (MID 7413)
- Command error (MID 0004 with error code 02: "Parameter set ID not present").

## MID 7413: Cycle/Pset - Phase/Step parameters data

Direction: Controller → Integrator

| Header   |      |     |             |            |            |       | Data Field               | Message End          |
|----------|------|-----|-------------|------------|------------|-------|--------------------------|----------------------|
| 0283     | 7413 | Rev | No Ack flag | Station ID | Spindle ID | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |             |            |            |       | 263 bytes                |                      |

This event telegram contains the cycle/Pset X - phase/step X settings stored in the controller.

The data field contains the following parameters:

### Revision 1:

| Parameter           | Field Id | Nb Bytes | Description  |
|---------------------|----------|----------|--|
| Spindle/Tool number | 01       | 2        | 01 to 99   |
| Cycle/Pset number   | 02       | 3        | 001, 002, ... to 250   |
| Phase/Step number   | 03       | 2        | 01, 02, ... to 40  |
| Phase/Step type     | 04       | 2        | Phase/Step type codes:<br>"S" = Search sequence<br>"D" = Rundown speed<br>"F" = Final speed / Tightening |

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 15/29      |                           |

|  |    |    |  |
|--|----|----|--|
|  |    |    | "R " = Run reverse / Loosening<br>"V " = Action on NOK<br>"J " = Jump<br>"T " = Prevailing Torque / Prevailing<br>"W " = Synchronization Waiting / Synchro<br>"d " = angle rundown<br>" " (2 space characters) = empty phase/step (end step)   |
| Tightening strategy type   | 05 | 2  | This field indicates the tightening strategy applied.<br>"0 " = Torque only (CVIxlI)<br>"1 " = Torque + Angle<br>"2 " = Torque + Angle + Torque Rate<br>"3 " = Angle + Torque<br>"4 " = Angle + Torque + Torque rate<br>"5 " = Torque + Current (CVIxlI)<br>"6 " = Torque + Angle + Current<br>"?? " or " " = not applicable |
| Min. torque  | 06 | 6  | Min. torque (value * 100)  |
| Max. torque  | 07 | 6  | Max. torque (value * 100)  |
| Safety/Abort torque  | 08 | 6  | Safety/Abort torque (value * 100)  |
| Angle threshold  | 09 | 6  | Angle threshold (value * 100)  |
| Target torque  | 10 | 6  | Target torque (value * 100)  |
| -  | 11 | 6  | Reserved   |
| Min. angle   | 12 | 6  | Min. angle (value * 10)  |
| Max. angle   | 13 | 6  | Max. angle (value * 10)  |
| Safety/Abort angle   | 14 | 6  | Safety/Abort angle (value * 10)  |
| Target angle<br>Back Angle 2 (Prevailing Backward)<br>End Angle (Prevailing Forward)   | 15 | 6  | Target angle (value * 10)  |
| -  | 16 | 6  | Reserved   |
| -  | 17 | 6  | Reserved   |
| -  | 18 | 6  | Reserved   |
| Interphase time/Post step delay  | 19 | 6  | Interphase time/Post step delay (in milliseconds)  |
| -  | 20 | 6  | reserved   |
| Speed / Downshift speed  | 21 | 6  | Speed/Downshift speed in %   |
| -  | 22 | 6  | Reserved   |
| -  | 23 | 6  | Reserved   |
| -  | 24 | 2  | Reserved   |
| -  | 25 | 6  | Reserved   |
| -  | 26 | 6  | Reserved   |
| Curve Index 1 (CVIxlI)   | 27 | 4  | Curve index start of phase point   |
| Curve Index 2 (CVIxlI)   | 28 | 4  | Curve index end of phase point   |
| -  | 29 | 6  | Reserved   |
| -  | 30 | 6  | Reserved   |
| -  | 31 | 6  | Reserved   |
| Direction/Rotation direction   | 32 | 2  | "CW" = Clockwise rotation of the motor<br>"CC" = counter clockwise rotation of the motor<br>"AL" = alternate rotation direction of the motor (search sequence only)  |
| Rotation type (CVIxlI search sequence,<br>Action on nok and Prevailing only)   | 33 | 1  | "A" = angle<br>"T" = time (CVIxlI)   |
| Rotation time/angle<br>Run reverse angle (Action on NOK)<br>Back Angle 1 (Prevailing Backward)<br>Start Angle (Prevailing Forward) | 34 | 3  | Time or angle depending on parameter 33<br>Angle range: 000-999° (accuracy 1°)<br>Time range: 00.0-99.9 sec. (accuracy 0.1 sec.)   |
| Number of rotations  | 35 | 1  | search sequence number of rotations  |
| Torque Unit  | 36 | 4  | "Nm " = Newton meter<br>"FtLb" = Foot pound<br>"InLb" = Inch pound<br>"Kgm " = Kilogram meter<br>"Kgcm" = Kilogram centimeter  |
| Cycle/Pset last modification date  | 37 | 19 | YYYY-MM-DD:HH:MM:SS  |

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 16/29      |                           |

## Revision 2:

| Parameter  | Field Id | Nb Bytes | Description   |
|--|----------|----------|---|
| Spindle/Tool number                              | 01       | 2        | 01 to 99  |
| Cycle/Pset number                                | 02       | 3        | 001, 002, ... to 250  |
| Phase/Step number                                | 03       | 2        | 01, 02, ... to 40   |
| Phase/Step type                                  | 04       | 2        | Phase/Step type codes:<br>"S " = Search sequence<br>"D " = Rundown speed<br>"F " = Final speed / Tightening<br>"R " = Run reverse / Loosening<br>"V " = Action on NOK<br>"J " = Jump<br>"T " = Prevailing Torque / Prevailing<br>"W " = Synchronization Waiting / Synchro<br>"d " = angle rundown<br>" <b>s</b> " = <b>seating detection</b><br>" <b>p</b> " = <b>post seating detection (CVIxlI)</b><br>" " (2 space characters) = empty phase/step (end step) |
| Tightening strategy type                         | 05       | 2        | This field indicates the tightening strategy applied.<br>"0 " = Torque only<br>"1 " = Torque + Angle<br>"2 " = Torque + Angle + Torque Rate<br>"3 " = Angle + Torque<br>"4 " = Angle + Torque + Torque rate<br>"5 " = Torque + Current<br>"6 " = Torque + Angle + Current6 -> Torque + Angle + Current<br>" <b>7</b> " = <b>Seating detection</b><br>" <b>8</b> " = <b>Post seating detection (CVIxlI)</b><br>"??"or " " = not applicable                       |
| Min. torque                                      | 06       | 6        | Min. torque (value * 100)   |
| Max. torque                                      | 07       | 6        | Max. torque (value * 100)   |
| Safety/Abort torque                              | 08       | 6        | Safety/Abort torque (value * 100)   |
| Angle threshold                                  | 09       | 6        | Angle threshold (value * 100)   |
| Target torque                                    | 10       | 6        | Target torque (value * 100)   |
| -  | 11       | 6        | reserved  |
| Min. angle                                       | 12       | 6        | Min. angle (value * 10)   |
| Max. angle                                       | 13       | 6        | Max. angle (value * 10)   |
| Safety/Abort angle                               | 14       | 6        | Safety/Abort angle (value * 10)   |
| Target angle                                     | 15       | 6        | Target angle (value * 10)   |
| Back Angle 2 (Prevailing Backward)               |          |          |   |
| End Angle (Prevailing Forward)                   |          |          |   |
| -  | 16       | 6        | Reserved  |
| -  | 17       | 6        | Reserved  |
| -  | 18       | 6        | Reserved  |
| Interphase time/Post step delay                  | 19       | 6        | Interphase time/Post step delay (in milliseconds)   |
| -  | 20       | 6        | Reserved  |
| Speed / Downshift speed                          | 21       | 6        | Speed/Downshift speed in %  |
| Target torque rate                               | 22       | 6        | Seating detection : Target torque rate (value * 10000)  |
| Angle delay                                      | 23       | 6        | Seating detection : Angle delay (value * 10)  |
| Nbr of samples for T.rate calc. / Angular sample | 24       | 2        | Seating detection : Nbr of samples for Torque rate calculation (range 00-64)  |
| Gradient torque (CVIxlI)                         | 25       | 6        | Post seating detection : Gradient torque (value * 100)  |
| Gradient angle (CVIxlI)                          | 26       | 6        | Post seating detection : Gradient angle (value * 10)  |
| Curve Index 1 (CVIxlI)                           | 27       | 4        | Curve index start of phase point  |
| Curve Index 2 (CVIxlI)                           | 28       | 4        | Curve index end of phase point  |
| -  | 29       | 6        | Reserved  |
| -  | 30       | 6        | Reserved  |



|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 17/29      |                           |

|  |    |    |   |
|--|----|----|---|
| -  | 31 | 6  | Reserved  |
| Direction/Rotation direction   | 32 | 2  | "CW" = Clockwise rotation of the motor<br>"CC" = counter clockwise rotation of the motor<br>"AL" = alternate rotation direction of the motor (search sequence only)               |
| Rotation type (CVIxlI search sequence, Action on nok and Prevailing only)  | 33 | 1  | "A" = angle<br>"T" = time (CVIxlI)  |
| Rotation time/angle<br>Run reverse angle (Action on NOK)<br>Back Angle 1 (Prevailing Backward)<br>Start Angle (Prevailing Forward) | 34 | 3  | Time or angle depending on parameter 33<br>Angle range: 000-999° (accuracy 1°)<br>Time range: 00.0-99.9 sec. (accuracy 0.1 sec.)  |
| Number of rotations  | 35 | 1  | 1 ASCII character   |
| Torque Unit  | 36 | 4  | "Nm " = Newton-metre<br>"FtLb" = Foot-pound<br>"InLb" = Inch-pound<br>"Kgm " = Kilogram-metre<br>"Kgcm"= Kilogram-centimeter<br>"Ncm " = Newton-centimeter<br>"InOz" = Inch-ounce |
| Cycle/Pset last modification date  | 37 | 19 | YYYY-MM-DD:HH:MM:SS   |

## **MID 7414: Change Cycle/Pset - Phase/Step parameters**

Direction     *Integrator → Controller*

| Header   |      |     |             |            |            |       | Data Field               | Message End          |
|----------|------|-----|-------------|------------|------------|-------|--------------------------|----------------------|
| 0256     | 7414 | Rev | No Ack flag | Station ID | Spindle ID | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |             |            |            |       | 236 bytes                |                      |

This command is used to write (set) a cycle/Pset – phase/step parameters in the controller.

The data field contains the following parameters to set in the server:

Possible answers:

- Command accepted (MID 0005) with 7414 in data field.
- Command error (MID 0004 with error code 02: "Parameter set ID not present").
- Command error (MID 0004 with error code 03: "Parameter set can't be set").

**Note:** For CVIxlI, only cycles with up to 6 phases can be modified.

This command can't be used with ELRT pulse tools and ERPHT tools.

# Desoutter Protocol

## Revision 1:

| Parameter   | Field Id | Nb Bytes | Description  |
|---|----------|----------|--|
| Spindle/Tool number                               | 01       | 2        | 01 to 99   |
| Cycle/Pset number                                 | 02       | 3        | 001, 002, ... to 250   |
| Phase/Step number                                 | 03       | 2        | 01, 02, ... to 40  |
| Phase/Step type<br>(Read only parameter)          | 04       | 2        | Phase/Step type codes:<br>"S" = Search sequence<br>"D" = Rundown speed<br>"F" = Final speed / Tightening<br>"R" = Run reverse / Loosening<br>"V" = Action on NOK<br>"J" = Jump<br>"T" = Prevailing Torque / Prevailing<br>"W" = Synchronization Waiting / Synchro<br>"d" = angle rundown<br>" " 2 spaces (not checked by the firmware).  |
| Tightening strategy type<br>(Read only parameter) | 05       | 2        | This field indicates the tightening strategy applied.<br>"0" = Torque only<br>"1" = Torque + Angle<br>"2" = Torque + Angle + Torque Rate<br>"3" = Angle + Torque<br>"4" = Angle + Torque + Torque rate<br>"5" = Torque + Current<br>"6" = Torque + Angle + Current6 -> Torque + Angle + Current<br>"??" or " " = not applicable<br>" " 2 spaces (not checked by the firmware). |
| Min. torque                                       | 06       | 6        | Min. torque (value * 100)  |
| Max. torque                                       | 07       | 6        | Max. torque (value * 100)  |
| Safety/Abort torque                               | 08       | 6        | Safety/Abort torque (value * 100)  |
| Angle threshold                                   | 09       | 6        | Angle threshold (value * 100)  |
| Target torque                                     | 10       | 6        | Target torque (value * 100)  |
| -   | 11       | 6        | reserved   |
| Min. angle  | 12       | 6        | Min. angle (value * 10)  |
| Max. angle  | 13       | 6        | Max. angle (value * 10)  |
| Safety/Abort angle                                | 14       | 6        | Safety/Abort angle (value * 10)  |
| Target angle                                      | 15       | 6        | Target angle (value * 10)  |
| Back Angle 2 (Prevailing Backward)                |          |          |  |
| End Angle (Prevailing Forward)                    |          |          |  |
| -   |          |          |  |
| -   | 16       | 6        | Reserved (spaces)  |
| -   | 17       | 6        | Reserved (spaces)  |
| -   | 18       | 6        | Reserved (spaces)  |
| Interphase time/Post step delay                   | 19       | 6        | Interphase time/Post step delay (in milliseconds)  |
| -   | 20       | 6        | Reserved (spaces)  |
| Speed / Downshift speed                           | 21       | 6        | Speed/Downshift speed in %   |
| -   | 22       | 6        | Reserved (spaces)  |
| -   | 23       | 6        | Reserved (spaces)  |
| -   | 24       | 2        | Reserved (spaces)  |
| -   | 25       | 6        | Reserved (spaces)  |
| -   | 26       | 6        | Reserved (spaces)  |
| Curve Index 1 (CVIxII)                            | 27       | 4        | Curve index start of phase point   |
| Curve Index 2 (CVIxII)                            | 28       | 4        | Curve index end of phase point   |
| -   | 29       | 6        | Reserved (spaces)  |
| -   | 30       | 6        | Reserved (spaces)  |
| -   | 31       | 6        | Reserved (spaces)  |
| Direction/Rotation direction                      | 32       | 2        | "CW" = Clockwise rotation of the motor<br>"CC" = counter clockwise rotation of the motor<br>"AL" = alternate rotation direction of the motor (search sequence only)  |

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 19/29      |                           |

|  |    |   |  |
|--|----|---|--|
| Rotation type (CVIxlI search sequence, Action on nok and Prevailing only)  | 33 | 1 | "A" = angle<br>"T" = time (CVIxlI)   |
| Rotation time/angle<br>Run reverse angle (Action on NOK)<br>Back Angle 1 (Prevailing Backward)<br>Start Angle (Prevailing Forward) | 34 | 3 | Time or angle depending on parameter 33<br>Angle range: 000-999° (accuracy 1°)<br>Time range: 00.0-99.9 sec. (accuracy 0.1 sec.) |
| Number of rotations  | 35 | 1 | 1 ASCII character  |

# Desoutter Protocol

## Revision 2:

| Parameter  | Field Id | Nb Bytes | Description   |
|--|----------|----------|---|
| Spindle/Tool number  | 01       | 2        | 01 to 99 Read only parameter  |
| Cycle/Pset number  | 02       | 3        | 001, 002, ... to 250 Read only parameter  |
| Phase/Step number  | 03       | 2        | 01, 02, ... to 40 Read only parameter   |
| Phase/Step type<br>(Read only parameter)   | 04       | 2        | Phase/Step type codes:<br>"S" = Search sequence<br>"D" = Rundown speed<br>"F" = Final speed / Tightening<br>"R" = Run reverse / Loosening<br>"V" = Action on NOK<br>"J" = Jump<br>"T" = Prevailing Torque / Prevailing<br>"W" = Synchronization Waiting / Synchro<br>"d" = angle rundown<br>" <b>s</b> " = <b>seating detection</b><br>" <b>p</b> " = <b>post seating detection</b><br>" " 2 spaces (not checked by the firmware).  |
| Tightening strategy type<br>(Read only parameter)                                    | 05       | 2        | This field indicates the tightening strategy applied.<br>"0" = Torque only<br>"1" = Torque + Angle<br>"2" = Torque + Angle + Torque Rate<br>"3" = Angle + Torque<br>"4" = Angle + Torque + Torque rate<br>"5" = Torque + Current<br>"6" = Torque + Angle + Current6 -> Torque + Angle + Current<br>" <b>7</b> " = <b>Seating detection</b><br>" <b>8</b> " = <b>Post seating detection</b><br>"??" or " " = not applicable<br>" " 2 spaces (not checked by the firmware). |
| Min. torque  | 06       | 6        | Min. torque (value * 100)   |
| Max. torque  | 07       | 6        | Max. torque (value * 100)   |
| Safety/Abort torque  | 08       | 6        | Safety/Abort torque (value * 100)   |
| Angle threshold  | 09       | 6        | Angle threshold (value * 100)   |
| Target torque  | 10       | 6        | Target torque (value * 100)   |
| -  | 11       | 6        | reserved  |
| Min. angle   | 12       | 6        | Min. angle (value * 10)   |
| Max. angle   | 13       | 6        | Max. angle (value * 10)   |
| Safety/Abort angle   | 14       | 6        | Safety/Abort angle (value * 10)   |
| Target angle<br>Back Angle 2 (Prevailing Backward)<br>End Angle (Prevailing Forward) | 15       | 6        | Target angle (value * 10)   |
| -  | 16       | 6        | Reserved (spaces)   |
| -  | 17       | 6        | Reserved (spaces)   |
| -  | 18       | 6        | Reserved (spaces)   |
| Interphase time/Post step delay  | 19       | 6        | Interphase time/Post step delay (in milliseconds)   |
| -  | 20       | 6        | Reserved (spaces)   |
| Speed / Downshift speed  | 21       | 6        | Speed/Downshift speed in %  |
| <b>Target torque rate</b>  | 22       | 6        | Seating detection : Target torque rate (value * 10000)  |
| <b>Angle delay</b>   | 23       | 6        | Seating detection : Angle delay (value * 10)  |
| <b>Nbr of samples for T.rate calc.</b>   | 24       | 2        | Seating detection : Nbr of samples for Torque rate calculation (range 00-64)  |
| <b>Gradient torque</b>   | 25       | 6        | Post seating detection : Gradient torque (value * 100)  |
| <b>Gradient angle</b>  | 26       | 6        | Post seating detection : Gradient angle (value * 10)  |
| Curve Index 1 (CVIxlI)   | 27       | 4        | Curve index start of phase point  |
| Curve Index 2 (CVIxII)   | 28       | 4        | Curve index end of phase point  |
| -  | 29       | 6        | Reserved (spaces)   |
| -  | 30       | 6        | Reserved (spaces)   |
| -  | 31       | 6        | Reserved (spaces)   |

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 21/29      |                           |

|  |    |   |   |
|--|----|---|---|
| Direction/Rotation direction   | 32 | 2 | "CW" = Clockwise rotation of the motor<br>"CC" = counter clockwise rotation of the motor<br>"AL" = alternate rotation direction of the motor (search sequence only) |
| Rotation type (CVIxlI search sequence, Action on nok and Prevailing only)  | 33 | 1 | "A" = angle<br>"T" = time (CVIxlI)  |
| Rotation time/angle<br>Run reverse angle (Action on NOK)<br>Back Angle 1 (Prevailing Backward)<br>Start Angle (Prevailing Forward) | 34 | 3 | Time or angle depending on parameter 33<br>Angle range: 000-999° (accuracy 1°)<br>Time range: 00.0-99.9 sec. (accuracy 0.1 sec.)                                    |
| Number of rotations  | 35 | 1 | 1 ASCII character   |

## 6. PSET selection & cordless tools

### ***MID 7418: Select PSET within time frame (ExBCom tool)***

Direction     *Integrator → CVI3 Controller*

| Header   |      |     |             |            |            |       | Data Field               | Message End          |
|----------|------|-----|-------------|------------|------------|-------|--------------------------|----------------------|
| 0029     | 7418 | Rev | No Ack flag | Station ID | Spindle ID | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |             |            |            |       | 9 bytes                  |                      |

This command is used to select a PSET in a given time frame.

This command is mostly used for cordless tools (ExBCom) to prevent WiFi lag issues.

| Parameter   | Bytes | Description                   |
|-------------|-------|-------------------------------|
| Pset number | 01-02 | 01                            |
|             | 03-05 | Pset number : 001, 002, etc.  |
| Time frame  | 06-07 | 02                            |
|             | 08-09 | Time frame 01 to 99 (x 100ms) |

#### Possible answers

- If Pset has been selected in the cordless tool within time frame (MID7419)
- If cordless tool response time is greater than defined time.  
Command error (MID 0004 with error code 79: "Command failed").
- If Pset does not exist:  
Command error (MID 0004 with error code 02: "Parameter set ID not present").
- If Pset selection source is not set to Open protocol :  
Command error (MID 0004 with error code 03: "Parameter set cannot be set").

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 23/29      |                           |

## ***MID 7419: PSET selected within time frame***

Direction     *CVI3 Controller → Integrator*

| Header   |      |     |             |            |            |       | Data Field               | Message End          |
|----------|------|-----|-------------|------------|------------|-------|--------------------------|----------------------|
| 0098     | 7419 | Rev | No Ack flag | Station ID | Spindle ID | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |             |            |            |       | 78 bytes                 |                      |

This command is sent by the controller when PSET has been selected within the given time frame from MID 7418.

| Parameter                | Bytes | Description         |
|--------------------------|-------|---------------------|
| Pset number              | 01-02 | 01                  |
|                          | 03-05 | 001, 002, etc.      |
| Time stamp               | 06-07 | 02                  |
|                          | 08-27 | YYYY-MM-DD:HH:MM:SS |
| Removable accessory name | 28-30 | 03                  |
|                          | 31-80 | 50 characters       |

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 24/29      |                           |

## 7. Get information data from controller or tool

Information Table: controller & tool information:

| Information number | Information description       | Data 1 | Data 2 | Data 3 |
|--------------------|-------------------------------|--------|--------|--------|
| 001                | Tool battery pack level       | 0-100% | -      | -      |
| 002                | Controller battery pack level | 0-100% | -      | -      |
|                    |                               |        |        |        |

### MID 7420: Information data subscribe

Direction     *Integrator* → *CVI3 Controller*

| Header   |      |     |             |            |            |       | Data Field               | Message End          |
|----------|------|-----|-------------|------------|------------|-------|--------------------------|----------------------|
| 0025     | 7420 | Rev | No Ack flag | Station ID | Spindle ID | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |             |            |            |       | 5 bytes                  |                      |

| Parameter          | Bytes | Description   |
|--------------------|-------|---|
| Information number | 01-02 | 01  |
|                    | 03-05 | Information number (001, 002, etc). (See <a href="#">Info table</a> ) |

This command is used to subscribe to an information from the controller or tool.  
At subscription, MID 7421 is returned by the controller with the actual data information.

Possible answers:

- Command accepted (MID 0005, with 7420 in data field)
- Command error (MID 0004 with error code 71: "Subscription already exists")
- Command error (MID 0004 with error code 79: "Command failed") in case information number doesn't exist.



|          |            |                             |
|----------|------------|-----------------------------|
| Part no  | 6159275850 | <h1>Desoutter Protocol</h1> |
| Issue no | 21         |                             |
| Language | English    |                             |
| Date     | 18/07/2016 |                             |
| Page     | 25/29      |                             |

## MID 7421: Information data change event

Direction     *CVI3 Controller → Integrator*

| Header       |      |     |             |            |            |       | Data Field               | Message End          |
|--------------|------|-----|-------------|------------|------------|-------|--------------------------|----------------------|
| 29 + N bytes | 7421 | Rev | No Ack flag | Station ID | Spindle ID | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes     |      |     |             |            |            |       | 9 + (N x 12 bytes)       |                      |

| Parameter            | Bytes   | Comment  |
|----------------------|---------|--|
| Information number   | 01-02   | 01   |
|                      | 03-05   | 001, 002, etc. (See <a href="#">Info table</a> )   |
| Number of Parameters | 06-07   | 02   |
|                      | 08-09   | Number of parameters of the information            |
| Information data 1   | 10-11   | 03   |
|                      | 12-21   | Data 1 value (10 characters)<br>Ex : “        52”. |
| Information data x   | 22-...  | 0#   |
|                      | ...-... | Data x value (10 characters)                       |

This command is returned by the controller if a subscription (MID7420) has been accepted. The information can contains one or several data. In that case the information data length depends on number of data.

## MID 7422: Information data change acknowledge

Direction     *Integrator → CVI3 Controller*

| Header   |      |     |             |            |            |       | Data Field | Message End          |
|----------|------|-----|-------------|------------|------------|-------|------------|----------------------|
| 0020     | 7422 | Rev | No Ack flag | Station ID | Spindle ID | Spare |            | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |             |            |            |       | 0 bytes    |                      |

This telegram must be sent by the integrator to acknowledge to the controller when the information data change event (MID 7421) has been successfully received.

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 26/29      |                           |

## ***MID 7423: Information data change unsubscribe***

Direction     *Integrator → CVI3 Controller*

| Header   |      |     |             |            |            |       | Data Field               | Message End          |
|----------|------|-----|-------------|------------|------------|-------|--------------------------|----------------------|
| 0025     | 7423 | Rev | No Ack flag | Station ID | Spindle ID | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |             |            |            |       | 5 bytes                  |                      |

| Parameter          | Bytes | Description   |
|--------------------|-------|---|
| Information number | 01-02 | 01  |
|                    | 03-05 | Information number (001, 002, etc). (See <a href="#">Info table</a> ) |

This command is used to stop receiving information data change event from the controller.

Possible answers:

- Command accepted (MID 0005, with 7423 in data field).
- Command error (MID 0004 with error code 72: "Subscription does not exist").
- Command error (MID 0004 with error code 79: "Command failed in case information number doesn't exist).

## ***MID 7424: Information data request***

Direction     *Integrator → CVI3 Controller*

| Header   |      |     |             |            |            |       | Data Field               | Message End          |
|----------|------|-----|-------------|------------|------------|-------|--------------------------|----------------------|
| 0025     | 7424 | Rev | No Ack flag | Station ID | Spindle ID | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes |      |     |             |            |            |       | 5 bytes                  |                      |

| Parameter          | Bytes | Description   |
|--------------------|-------|---|
| Information number | 01-02 | 01  |
|                    | 03-05 | Information number (001, 002, etc). (See <a href="#">Info table</a> ) |

This command is used to get an information data from the controller or tool.

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 27/29      |                           |

## ***MID 7425: Information data reply***

Direction      *CVI3 Controller → Integrator*

| Header       |      |     |             |            |            |       | Data Field               | Message End          |
|--------------|------|-----|-------------|------------|------------|-------|--------------------------|----------------------|
| 29 + N bytes | 7425 | Rev | No Ack flag | Station ID | Spindle ID | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes     |      |     |             |            |            |       | 9 + (N x 12 bytes)       |                      |

| Parameter            | Bytes   | Description                                      |
|----------------------|---------|--|
| Information number   | 01-02   | 01   |
|                      | 03-05   | 001, 002, etc. (See <a href="#">Info table</a> ) |
| Number of Parameters | 06-07   | 02   |
|                      | 08-09   | Number of parameters of the information          |
| Information data 1   | 10-11   | 03   |
|                      | 12-21   | Data 1 value (10 characters)<br>Ex : "      52". |
| Information data x   | 22-...  | 0#   |
|                      | ...-... | Data x value (10 characters)                     |

This command is returned by the controller if a request (MID7440) has been accepted.  
The information can contains one or several data. In that case the information data length depends on number of data.

|          |            |                           |
|----------|------------|---------------------------|
| Part no  | 6159275850 | <b>Desoutter Protocol</b> |
| Issue no | 21         |                           |
| Language | English    |                           |
| Date     | 18/07/2016 |                           |
| Page     | 28/29      |                           |

## 8. File transfer

### ***MID 7427: Transfer file (Pset settings)***

Direction     *Integrator → CVI3 Controller*

| Header       |      |     |             |            |            |       | Data Field               | Message End          |
|--------------|------|-----|-------------|------------|------------|-------|--------------------------|----------------------|
| 37 + N bytes | 7427 | Rev | No Ack flag | Station ID | Spindle ID | Spare | Data<br>(See next table) | NULL<br>(ASCII 0x00) |
| 20 bytes     |      |     |             |            |            |       | 17 + N bytes             |                      |

This command is sent by the client to write a Pset or a Removable accessory file in the controller.

| Parameter   | Bytes  | Description   |
|-------------|--------|---|
| File type   | 01-02  | 01  |
|             | 03-05  | 001: Pset file ( *.dex file exported from CVI Config ).<br>002: Removable accessory file ( <i>not available</i> ) |
| Nb of parts | 06-07  | 02  |
|             | 08-10  | 001, 002, etc.  |
| Part Id     | 11-12  | 03  |
|             | 13-15  | 001, 002, etc.  |
| File part   | 16-17  | 04  |
|             | 18-... | N < Max Size (9970)   |

Possible answers

- Command accepted (MID 0005, with 7427 in data field).
- Command error (MID 0004 with error code 79: "Command failed) in case of error on file type, number or parts, part id or invalid data.

# Desoutter Protocol

## 9. Synthesis

| MID                  | Description                         | CVIxlII | CVI3    |
|----------------------|-------------------------------------|---------|---------|
| <a href="#">7400</a> | System event (Reserved)             | 4.2A    | N/A     |
| <a href="#">7402</a> | Cycle & phases results subscribe    | 4.2A    | N/A     |
| <a href="#">7403</a> | Cycle & phases results unsubscribe  | 4.2A    | N/A     |
| <a href="#">7404</a> | Phase result data                   | 4.2A    | N/A     |
| <a href="#">7405</a> | Phase result data acknowledge       | 4.2A    | N/A     |
| <a href="#">7406</a> | Cycle result data                   | 4.2A    | N/A     |
| <a href="#">7407</a> | Cycle result data acknowledge       | 4.2A    | N/A     |
| <a href="#">7408</a> | Last tightening curve subscribe     | 4.2A    | 1.6.6.x |
| <a href="#">7409</a> | Last tightening curve unsubscribe   | 4.2A    | 1.6.6.x |
| <a href="#">7410</a> | Last tightening curve data          | 4.2A    | 1.6.6.x |
| <a href="#">7411</a> | Last tightening curve acknowledge   | 4.2A    | 1.6.6.x |
| <a href="#">7412</a> | Cycle/Pset parameters request       | 4.2A    | 1.6.9.x |
| <a href="#">7413</a> | Cycle/Pset parameters data          | 4.2A    | 1.6.9.x |
| <a href="#">7414</a> | Change Cycle/Pset parameters        | 4.2A    | 1.6.9.x |
| <a href="#">7418</a> | Select Pset within time frame       | N/A     | 1.6.6.x |
| <a href="#">7419</a> | Pset selected within time frame     | N/A     | 1.6.6.x |
| <a href="#">7420</a> | Information data change subscribe   | N/A     | 1.6.6.x |
| <a href="#">7421</a> | Information data change event       | N/A     | 1.6.6.x |
| <a href="#">7422</a> | Information data change acknowledge | N/A     | 1.6.6.x |
| <a href="#">7423</a> | Information data change unsubscribe | N/A     | 1.6.6.x |
| <a href="#">7424</a> | Information data request            | N/A     | 1.6.6.x |
| <a href="#">7425</a> | Information data reply              | N/A     | 1.6.6.x |
| <a href="#">7427</a> | Transfer file (Pset settings)       | N/A     | 1.6.6.x |
|                      |                                     |         |         |